

The Linux Print2Win mini-HOWTO

Table of Contents

The Linux Print2Win mini-HOWTO	1
Marcelo Pereira da Silva, marcelo@pereira.com	1
1. Introduction	1
2. Server (Windows)	1
3. Client (Linux)	1
4. /etc/printcap TIPS	1
5. License	1
6. Credits	1
1. Introduction	1
2. Server (Windows)	1
3. Client (Linux)	1
3.1 Standard lpr	2
4. /etc/printcap TIPS	2
5. License	3
6. Credits	3

The Linux Print2Win mini-HOWTO

Marcelo Pereira da Silva, marcelo@pereira.com

v1.1, Jan 2002

This howto contains the general configuration to get linux printing to a Windows print share.

1. [Introduction](#)

2. [Server \(Windows\)](#)

3. [Client \(Linux\)](#)

- [3.1 Standard lpr](#)

4. [/etc/printcap TIPS](#)

5. [License](#)

6. [Credits](#)

1. [Introduction](#)

As we want the print service running, let set up all the environment step by step, to avoid mistakes or bad configurations.

First, set up the server, so when you have the server running, go to the clients and configure them.

2. [Server \(Windows\)](#)

There is no special rules when configuring the server. Just install the printer driver in the Windows server, test it to certificate the printer is running properly, so share the printer.

3. [Client \(Linux\)](#)

The setup of the client is almost the same when you are setting up the printcap to print linux to linux, with some changes.

3.1 Standard lpr

The simplest way to do it is adding an entry in `/etc/printcap`. As a quick example, the entry for a generic matricial printer would be:

```
# EPSON LX300
epson:\
    :sd=/var/spool/lpd/epson:\
    :mx#0:\
    :sh:\
    :if=/var/spool/lpd/epson/filter:\
    :lp=/dev/null:
```

* Make sure you are using the correct filter, or the right generic one.

Be sure you have created the directory `/var/spool/lpd/epson`, and the users you wish to use the printer have the right access to this.

For example, let the Windows Print Server be called by `meriadoc`, it IP=`192.168.1.49` and the printer (at Windows) are shared as `epsonLX`.

So, you have to configure `/var/spool/lpd/epson/.config` like this:

```
share='\\meriadoc\epsonLX'
hostip=192.168.1.49
```

Where:

- `share='\\windows-print-server-name\print-share-name'`
- `hostip=windows-print-server-IP`

Once your `/etc/printcap` is configured, you have to enable the print share:

```
[localhost]$ lpc up epson
[localhost]$ lpc enable epson
```

If everything is ok, you can send jobs to the queue:

```
[localhost]$ lpr -Pepson <file>
```

4. [/etc/printcap TIPS](#)

I have used the entry below in the first example, but this is not a particularly good idea:

```
...
    :lp=/dev/null:\
```

Because `lpr` does an 'exclusive' open on the file you specify as `lp=`. It does this in order to prevent multiple processes from trying to print to the same printer at the same time.

The side effect of this is that in your case, eng and colour can't print at the same time, (usually more or less transparent since they probably print quickly and since they queue you probably don't notice) but any other process that tries to write to /dev/null will break!

On a single user system, probably not a big problem. I have a system with over 50 printers. It would be a problem there.

The solution is to create a dummy printer for each. Eg: touch /dev/eng.

```
[localhost]$ touch /dev/eng  
[localhost]$ touch /dev/colour
```

5. License

This document, Print2Win-HOWTO, is copyrighted (c) 2001-2002 by Marcelo Pereira da Silva. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1 or any later version published by the Free Software Foundation; with no Invariant Sections, with no Front-Cover Texts, and with no Back-Cover Texts. A copy of the license is available at <http://www.gnu.org/copyleft/fdl.html>.

6. Credits

Thanks to all those who sent opinions about this document, to everybody who told me some printing tips, to Rick Bressler, and a special thanks to Harish Pillay, whose I don't know, but wrote the first version of this document.
